


# LEAF SAP SAMPLING GUIDE

## Soybean



### Keep in mind!

- Avoid outer rows and first 20 feet of a row.
- Sample leaves with average leaf quality. Sample areas of abnormal growth separately.
- Sample consistently; sunny side of plant, avoid extreme weather etc.
- If leaves are wet at sampling lightly pat dry before shipping (moisture influences results).
- Sap Analysis data works best when used in progression. The more samples the better crop nutrient uptake can be illustrated and understood.
- Note fertilizer and irrigation times and application rates if possible.
- Sample either before or 3+ days after fertilizer/pesticides have been applied.



### Sampling Instructions

**Sample Time:** Sample in the morning before 11 a.m. and temperatures less than 80 °F for adequate leaf tension and moisture. Avoid sampling in the rain. Store samples in cooler.

**Sample Size:** Collect 80+ grams each of both new (young) and old trifoliolate leaves + petiole for a collected total of 160+ grams per sample set. Bag new and old leaves separately in zip lock bags labeled New and Old.

**Initial Sampling:** Begin sampling when plant develops 1st trifoliolate leaf. Collect NEW fully developed trifoliolate leaves + petiole only. Place stacked trifoliolate leaves + petiole in zip lock bag labeled NEW. Growth stage: V2

**Sequential Samples:** New & Old trifoliolate leaf set every 2+ weeks in conjunction with growth stages: V4-V12, R1 (beginning bloom), R2 (full bloom), R3 (beginning pod), R4 (pod fill) and pre-harvest.

**NEW-** Youngest fully expanded trifoliolate leaves + petiole. Place stacked trifoliolate leaves + petiole in zip lock bag labeled NEW.

**New leaf = newest yet fully developed trifoliolate leaf**


**OLD-** Oldest still healthy and functional trifoliolate leaves + petiole. Place stacked trifoliolate leaves + petiole in separate zip lock bag labeled OLD.

**Old leaf = oldest yet still viable trifoliolate leaf**


**\*\*Do not mix varieties when sampling as this may cause variation in analyses\*\***

# LEAF SAP SAMPLING GUIDE

## Soybean



Sample entire trifoliate leaf with petiole



Drawn by In-house artist, Jose Aburto. Property of NEW AGE Laboratories

V 1

V 3

R 1

R 3

R 5

R 8

Keep samples cool. Ship overnight or 2-day on M/T/W (morning arrival time) with ice packs. Samples should not come into direct contact with ice packs. Let air out of bags before shipping.

All samples must be accompanied by a fully completed Sample Submission Form. Fillable version available on our website [www.newagelaboratories.com](http://www.newagelaboratories.com).

Science You Can Use, Partners You Can Trust

160 Veterans Blvd, South Haven, MI 49090

(269) 637-5658

(888)-685-1628